# **NetSim Multi-Parameter Sweep Program**

Software: NetSim v13.0 (32/64 bit), DOT NET CORE SDK 3.1, Python 3.7.4

### **Project Download Link:**

https://github.com/NetSim-TETCOS/Multi-Parameter-Sweeper v13.0/archive/refs/heads/main.zip

Follow the instructions specified in the following link to download and setup the Project in NetSim:

https://support.tetcos.com/en/support/solutions/articles/14000128666-downloading-and-setting-up-netsim-file-exchange-projects

#### Introduction

When users want to *sweep* one or more parameters, they change their values between simulation runs, and compare and analyse the performance metrics from each run. NetSim multi-parameter sweeper enables users to automate the sweep process.

Consider an example, where a user wishes to create and simulate a network scenario for all possible values of one or more parameters in combination and analyse a set of performance metrics across the simulation runs. This is extremely time consuming to do manually using the NetSim GUI.

The multi-parameter sweep program enables users to automate the sweep process across multiple input parameters, simulate each run, save each result, and compare specific output metrics via a spreadsheet software like MS Excel.

The sweep program runs NetSim via its CLI interface.

# **File Organization**

The project directory consists of several binaries which are responsible for different tasks during a multi-parameter sweep:




Figure 1: project directory consists of several binaries

1. **input.xml**: This file contains the base NetSim network configuration that is to be simulated. This file is created by copy pasting the Configuration.netsim file that can be obtained by saving a network configuration in NetSim and renaming it to input.xml.

```
Tile Edit View Project Debug XML Test Analyze Tools
G - 🖯 🏗 - 🏝 💾 🧬 り - 🤆
                                                ▶ Attach... - 🎜 🎑 _
                                                                                              |  Live Share
          <?xml version="1.0" encoding="UTF-8" standalone="no"?>
        EKTETCOS_NETSIM xmlns:ns0="http://www.w3.org/2001/XMLSchema-instance" ns0:noNamespaceSchema
           <EXPERIMENT_INFORMATION>...
           <GUI INFORMATION>...
           <NETWORK_CONFIGURATION>
              <DEVICE_CONFIGURATION DEVICE_COUNT="4">
                kDEVICE DEFAULT_DEVICE NAME="gNB" DEVICE_ID="1" DEVICE_IMAGE="gNB.png" DEVICE_NAME
kDEVICE DEFAULT_DEVICE_NAME="EPC" DEVICE_ID="2" DEVICE_IMAGE="EPC.png" DEVICE_NAME
                <DEVICE DEFAULT DEVICE NAME="UE" DEVICE ID="4" DEVICE IMAGE="UserEquipment.p"</pre>
              </DEVICE CONFIGURATION>
                KLINK DEVICE COUNT="2" LINK COLOR="" LINK ID="1" LINK MODE="FULL DUPLEX" LINK NAME:
                KLINK DEVICE COUNT="2" LINK COLOR="" LINK ID="2" LINK MODE="FULL DUPLEX" LINK NAME:
              <APPLICATION_CONFIGURATION COUNT="1">
                KAPPLICATION APPLICATION COLOR=
                                                  "0x9000ffff" APPLICATION METHOD="UNICAST" APPLICATION
              </APPLICATION_CONFIGURATION>
             ALETHORY CONFICURATION
                                                                                         Ln: 212 Ch: 1 SPC CRLF
```

Figure 2: NetSim input Configuration.netsim file

The values of parameters which are to be varied during each simulation run needs to be specified as {0}, {1}, {2}, etc. respectively.

For Example, if the X and Y coordinates of a device is to be varied the values can be modified in the input.xml file as shown below:

```
File Edit View Project Debug XML Test Analyze Tools
                                                          Extensions Window Help
 G - 🖯 🏗 - 造 🖺 🚜 り - 🤉
                                                          ▶ Attach... - 🎜 🚳 _
            <?xml version="1.0" encoding="UTF-8" standalone="no"?>
       2 📮<TETCOS_NETSIM xmlns:ns0="http://www.w3.org/2001/XMLSchema-instance" ns0:noNamespaceScheme
              <GUI INFORMATION>...
     18 = 19 = 20 ± 68 ±
               <NETWORK_CONFIGURATION>
                 <DEVICE_CONFIGURATION DEVICE_COUNT="4">
                   CDEVICE DEFAULT DEVICE NAME="gNB" DEVICE ID="1" DEVICE IMAGE="gNB.png" DEVICE NAME:

CDEVICE DEFAULT DEVICE NAME="EPC" DEVICE ID="2" DEVICE IMAGE="EPC.png" DEVICE NAME:

CDEVICE DEFAULT DEVICE NAME="Wired Node" DEVICE_ID="3" DEVICE_IMAGE="WiredNode.png"
    169 E
                    <DEVICE DEFAULT DEVICE NAME="UE" DEVICE ID="4" DEVICE_IMAGE="UserEquipment.png" DEVI</pre>
                        POS_3D X_OR_LON="{0}" Y_OR_LAT="{1}"
<MOBILITY MODEL="NO_MOBILITY"/>
                      <INTERFACE ID="1" INTERFACE TYPE="LTE NR">
                         <LAYER TYPE="NETWORK_LAYER">
                           <NETWORK PROTOCOL NAME="IPV4" SETPROPERTY="TRUE">
                             <PROTOCOL PROPERTY DEFAULT GATEWAY="11.2.1.1" IP ADDRESS="11.2.1.2" SUBNET I</pre>
                       ← → ( TVDE_"DATALTMIK I AVED"
         ② 0 ▲ 2
                                                                                                     ln: 169 Ch: 53 SPC CRLF
```

Figure 3: Modify X and Y coordinates in input input.xml file

2. **Script.txt:** This file should be updated with the parameter from the output metrics of NetSim that is to be logged at the end of each simulation run for the purpose of analysis.

At the end of every simulation, NetSim generates a Metrics.xml file which contain the performance metrics written in a specific format based on which it is loaded in the results dashboard.

Each Metric is part of a results table which can be accessed using a menu in the results dashboard. A NetSim Metrics.xml file is shown below:

```
File Edit View Project Debug XML Test Analyze Tools Extensions Window Help Search (Ctrl+Q)
                                                                                                                                          Live Share
     383 ☐ <MENU Name="Application_Metrics">
             <TABLE name="Application_Metrics">
              <TH name="Application Id" isShow="true"/>
                <TH name="Throughput Plot" isShow="true"/>
<TH name="Application Name" isShow="true"/>
               <TH name="Packet generated" isShow="true"/>
<TH name="Packet received" isShow="true"/>
                <TH name="Payload generated (bytes)" isShow="false"/>
                <TH name="Payload received (bytes)" isShow="false"/>
                <TH name="Throughput (Mbps)" isShow="true"/>
                <TH name="Delay(microsec)" isShow="true"/>
<TH name="Jitter(microsec)" isShow="true"/>
                 <TC Value="1"/>
                  <TC Value="App1_CBR"/>
                 <TC Value="25000"/
                 <TC Value="36500000"/>
<TC Value="26201160"/>
                <TC Value="4192.185600"/>
<TC Value="7188.952970"/>
                                                                                                                                     Ln: 458 Ch: 1 SPC
```

Figure 4: NetSim output Metrics.xml file

For Example, if the application throughput is to be logged for each simulation run then the script file can be updated as shown below:




Figure 5: The application throughput is to be logged for each simulation modified in Script.txt

- 3. **ConfigWriter.exe**: This executable takes one or more command line arguments as input and generated Configuration.netsim file by replacing the arguments in place of the variable parameters specified in the input.xml file.
  - If there are two variable parameters specified in the input.xml file ({0} and {1}) then two arguments need to be passed while calling ConfigWriter.exe.
- 4. **MetricsReader.exe**: This executable is responsible for reading the output parameter from the Metrics.xml file generated after each simulation and logging it to the results file.

Users the Script.txt file to determine which parameter to read from the Metrics file.

If multiple parameters are to be read and logged, then the MetricsReader.exe can be called multiple times with Script.txt file having information about the parameter to be read each time.




Figure 6: Distance Vs. Throughput obtained in result.csv

- 5. **Supporting DLL's**: Some the supporting files such as ConfigWriter.dll, MetricsReader.dll, NetSimMetricsReader.dll, NetSimXmlReader.dll, etc. which are present in the project folder are used by other executable such as ConfigWriter.exe and MetricsReader.exe for various purposes during a multi-parameter sweep.
- 6. **runTest.py** uses python programming language which is less complex and offers more flexibility as the number of input and output parameters increases.

Users can also write the script to run the multi-parameter sweep process in a preferred programming language as per the convenience.

The script can be configured to run multiple simulation iterations based on the number of parameters to be varied and the range of values of each parameter.

NETSIM\_PATH variable can be set to the path of NetSim 32-bit/64-bit binaries in the install directory or workspace which is to be used to run Simulations.

```
File Edit View Git Project Debug Test Analyze Tools Extensions Window Help Search (Ctrl+Q)
                                                                                                                                           o ×
                                                0-0 8-6 9-6-1
                                                                                                                                       import random
            import shutil
import math
             import sys
                 the path of NetSim Binaries to be used for simulation. Either 32 bit or 64 bit
           NETSIM_PATH="C:\\Users\\HP\\Documents\\NetSim_13.0.26_64_std_default\\bin\\bin_x64"
            #Set NETSIM_AUTO environment variable to avoid keyboard interrupt at the end of each simulation
            os.environ['NETSIM AUTO'] = '1
             #Create IOPath directory to store the input Configuration.netsim file and the simulation output files during each iteration
           = if not os.path.exists('IOPath'):
                os.makedirs('IOPath')
             #Create Data directory to store the Configuration.netsim and the Metrics.xml files associated with each iteration
       18
           Fif not os.path.exists('Data'):
                os.makedirs('Data')
            #Clear the IOPath folder if it has any files created during previous multi-parameter sweep runs
       21
           ofor root, dirs, files in os.walk('IOPath'):
for file in files:
                    os.remove(os.path.join(root, file))
           #Clear the Data folder if it has any files created during previous multi-parameter sweep runs

of root, dirs, files in os.walk('Data'):

No BUSUSTOUND
```

Figure 7: User need to set NetSim Path based on 32/64-bit

#### For example,

64-bit:

NETSIM\_PATH="C:\\Users\\HP\\Documents\\NetSim\_13.0.26\_64\_std\_default\\bin\\bin\_x64"

32-bit:

NETSIM\_PATH="C:\\Users\\HP\\Documents\\NetSim\_13.0.26\_32\_std\_default\\bin\\bin\_x86" <\li>license information> - License server details or the path of license file in case of node locked or cloud licenses

```
File Edit View Git Project Debug Test Analyze Tools Extensions Window Help Search (Ctrl+Q)
                                                                      ☑ Live Share  欠
0-0 8-6 4 5-6-
           52
                              os.remove("IOPath\Metrics.xml")
           53
54
55
56
57
58
59
60
61
62
63
64
65
66
67
                        #Call ConfigWriter.exe with arguments as per the number of variable parameters in the input.xml file cmd='ConfigWriter.exe '+str(i)
                        print(cmd)
                        os.system(cmd)
                        #Copy the Configuration.netsim file generated by ConfigWriter.exe to IOPath directory
if(os.path.isfile("Configuration.netsim")):
    shutil.copy("Configuration.netsim","IOPath\Configuration.netsim")
                      #Run NetSim via CLI mode by passing the apppath iopath and license information to the NetSimCore.ex cmd=NETSIM_PATH+"\\NetSimcore.exe -apppath "+NETSIM_PATH+" -iopath 10Path -license 5053@127.0.0.1"
                        #print(cmd)
           68
69
                        #Create a copy of the output Metrics.xml file for writing the result log
if(os.path.isfile("IOPath\Metrics.xml")):
           70
71
72
                              shutil.copy("IOPath\Metrics.xml","Metrics.xml")
                         #Number of Script files i.e Number of Output parameters to be read from Metrics.xml
                        #If only one output parameter is to be read only one Script text file with name Script.txt to be provided
#If more than one output parameter is to be read, multiple Script text file with name Script1.txt, Script2.txt,...
#...,Scriptn.txt to be provided
           73
74
                        OUTPUT PARAM COUNT=1:
                                                                                                                                                                                                Ln: 45 Ch: 48 SPC
```

Figure 8: User need to set NetSim Path based on 32/64-bit and license file server information

# For Example,

Server based license (<port no>@<server ip address>):

cmd=NETSIM\_PATH+"\\NetSimcore.exe -apppath "+NETSIM\_PATH+" -iopath IOPath -license 5053@192.168.0.9"

Node Locked or Cloud licenses (path of license file):

cmd=NETSIM\_PATH+"\\NetSimcore.exe -apppath "+NETSIM\_PATH+" -iopath IOPath -license "+"\"C:\\Program Files\\NetSim\\Standard\_v13\_0\\bin\\""

# **Running a Multi-Parameter Sweep process:**

# Example 1: Modifying a single input parameter and logging a single output parameter

Consider the following network 5G network scenario in NetSim, comprising of a Wired Node, Router, gNB and a UE.




Figure 9: Network Topology

The network configuration has the initial distance between the gNB and UE as 50 meters with the gNB located at (1000,200) and UE located at (1000,250).

Multi-Parameter Sweeper is configured to run simulations for different distance between the gNB and UE by varying the UE Y coordinate value from 250 to 400 in steps of 50 meters.

 The network scenario is saved and the content of the Configuration.netsim file is copied to the Multi-Parameter-Sweeper directory and renamed as input.xml.
 Refer to the Example 1 directory which is part of the project folder (Multi-Parameter-Sweeper v13.0\Examples\Multi-Parameter-Sweeper-Example-1)




Figure 10: Renamed Configuration.netsim to input.xml and pasted in Multi-Parameter-Sweeper directory

The value of the Y coordinate of UE that is to be modified during each simulation run is updated ("{0}") in the configuration file as shown below:

```
| Part | First | First
```

Figure 11: Modified Y coordinate of UE in input.xml

The Script.txt file is updated with the details of the output parameter to be read from the Metrics.xml file and added to the result csv log file. In this case the Application throughput is to be logged for each simulation run.



Figure 12: The application throughput is to be logged for each simulation modified in Script.txt

3. runTest.py is updated to pass the Y coordinate value during each iteration to generate Configuration file run simulation and update the result csv log.

The runTest.bat batch script modified for running simulations for different values of Y coordinates starting from 250 up to 400 in steps of 50 is shown below:

- A result.csv file is created and added with headings Y and Throughput (Mbps).
- For loop is set to iteratively run simulations for values starting from 250 to 400 in steps of 50.
- The value of the parameter Y in the current iteration is written to the result log file for analysis.
- The value of the parameter Y in the current iteration is passed as input to ConfigWriter executable to generate Configuration.netsim file for each simulation.
- NetSim simulation is run via CLI mode by passing the apppath, iopath and license server information
- Configuration file and Metrics file are copied and renamed appending the value of the parameter in the current iteration.

The runTest.py python script modified for running simulations for different values of Y coordinates starting from 250 up to 400 in steps of 50 is shown below:

```
*** Set We Get Project Debuy Text Analyze Tools Extensions Window Help Search (Chi-C) A Solution

*** Attach...** Page *** Attach...**
```

Figure 13: To Create result.csv file, added with headings Y and Throughput (Mbps) and NetSim installation Path

- NETSIM\_PATH variable is set to the path of NetSim 32-bit/64-bit binaries in the install directory or workspace in the system.
- A result.csv file is created and added with headings Y and Throughput (Mbps).

Figure 14: Varying Distance and set license server information

- For loop is set to iteratively run simulations for values starting from 250 to 400 in steps of 50.
- The value of the parameter Y in the current iteration is passed as input to ConfigWriter executable to generate Configuration.netsim file for each simulation.
- NetSim simulation is run via CLI mode by passing the apppath, iopath and license server information.

```
| Description | Property | Proper
```

Figure 15: Modify parameters in runTest.py

- The value of the parameter Y in the current iteration is written to the result log file for analysis.
- Configuration file and Metrics file are copied and renamed appending the value of the parameter in the current iteration.
- 4. Multi-Parameter Sweeping process is started by opening command prompt in the directory of the Multi-Parameter-Sweeping project and starting the python script as shown below:



Figure 16: Running python script using cmd prompt

This starts the Multi-Parameter-Sweeping process which runs NetSim simulations iteratively for different values of Y parameter of UE.

At the end of the process the Multi-Parameter-Sweeping folder will have the following file and folders created:




Figure 17: After Simulation Multi-Parameter-Sweeping folder contains output files like result.scv, Data etc

 Data: Contains multiple folders corresponding to each simulation run, with its name including the value of the parameters in that iteration.




Figure 18: Based on distance Configuration.netsim files created in output folder

Each folder contains the all the output files associated with the simulation run.




Figure 19: Each folder contains the all the output files

- **IOPath**: Used for storing the Configuration.netsim file and the simulation files generated during each simulation run.
- Result.csv: This is the output log which contains the parameter varied during each simulation run and the output parameter associated with each run.




Figure 20: Distance Vs. Throughput obtained in result.csv

#### Varying multiple network parameters

In order to vary multiple network parameters during the multi-parameter sweep process each parameter in the input.xml file can be modified as {0},{1},{2},{3},...{n} respectively.

# Logging multiple output parameters

Each output parameter that is to be logged should be part of the Script.txt file. However, the Script.txt file should contain only the details of one output parameter during the call to MetricsReader.exe. To log multiple parameters, multiple script files can be used. If n output parameters are to be logged, then there can be script1.txt, script2.txt, script.txt in the sweeper folder. For Example, there can be two Script files as shown below:




Figure 21: Multiple output parameters

# Example 2: Modifying multiple input parameters and logging multiple output parameter

Consider the following network 5G network scenario in NetSim, comprising of a Wired Node, Router, gNB and a UE.




Figure 22: Network Scenario

Properties configured in the LTE\_NR interface of the gNB is shown in the table below:

Interface(5G_RAN) Properties	
Tx_Power(dBM)	40
Tx_Antenna_Count	8
Rx_Antenna_Count	4
CA_Type	Single Band
CA_Configuration	n78
CA_Count	1
MU	0

Channel Bandwidth (MHz)	10
PRB Count	52
MCS Table	QAM64
CQI Table	Table 1
X_Overhead	XOH0
DL UL Ratio	4:1
Outdoor Scenario	Rural Macro
LOS Mode	Standard
Wireless Link Properties	
Channel Characteristics	No_Pathloss
Wired Link Properties	
Link Speed (Mbps)	10000
BER	0
Propagation Delay (µs)	0
Application Properties	
Packet Size (Byte)	1460
Inter Arrival Time (µs)	166
Generation Rate (Mbps)	100
Transport Control	UDP
Start Time (s)	1
QoS	BE
Simulation Parameters	
Simulation Time (s)	1.1
· · · · · · · · · · · · · · · · · · ·	

Table 1: gNB Properties

Traffic is generated at a rate of 70 Mbps and upon running simulation, the throughput achieved is 59.95 Mbps.

We now find the max throughput for each possible bandwidth; Tx Antenna count and Rx Antenna count combination varying the generation rate based accordingly.

Two more parameters to be taken care include, the PRB Count and Guard Band (KHz) which vary with respect to the bandwidth.

Input Variables	Value Range
Channel Bandwidth (MHz)	10,15,20,25,30,40,50
Tx_Antenna_Count	1,2,4,8,16,32,64,128
Rx_Antenna_Count	1,2,4,8,16
PRB Count	52,79,106,133,160,216,270
Guard Band (KHz)	312.5,382.5,452.5,522.5,592.5,552.5,692.5
Reference Inter Arrival Time	166
(Microseconds)	
Reference Bandwidth	10
Reference DL MIMO Layer Count	2

Table 2: Input variable values

Inter Arrival Time for each case is calculated based on the Reference IAT Bandwidth and DL MIMO Layer Count as shown below:

$$Inter\ Arrival\ Time\ (Micro\ Seconds) = \frac{Ref\ IAT}{\left(\frac{Curr\ BW}{Ref\ BW}\right)*\left(\frac{Curr\ DL\ MIMO\ Count}{Ref\ DL\ MIMO\ Count}\right)}$$

For E.g. In case of Bandwidth of 20 MHz and DL MIMO Count of 4 inter arrival time is

Inter Arrival Time (Micro Seconds) = 
$$\frac{166}{\left(\frac{20}{10}\right)*\left(\frac{4}{2}\right)} = 41.5 \text{ Mbps}$$

- 1. The network scenario is saved and the content of the Configuration.netsim file is copied to the Multi-Parameter-Sweeper directory and renamed as input.xml.
- 2. Refer to the Example 2 directory which is part of the project folder (Multi-Parameter-Sweeper\_v13.0\Examples\Multi-Parameter-Sweeper-Example-2).




Figure 23: Renamed Configuration.netsim to input.xml and pasted in Multi-Parameter-Sweeper directory

3. In the Input.xml file the value of the input variables are modified as shown in the table below:

Input Variables	
Channel Bandwidth (MHz)	{0}
Tx Antenna Count	{1}
Rx Antenna Count	{2}
Inter Arrival Time (Microseconds)	{3}
PRB Count	{4}
Guard Band (KHz)	{5}

Table 3: Variables are modified to the input.xml file

Figure 24: The above table 3 Variables are modified in input.xml file

4. The python script runTest.py is modified to run simulation for all possible combinations of Bandwidth and Tx Antenna Count and Rx Antenna Count with the respective values of Guard Band, PRB Count and the IAT that is calculated.




Figure 25: Modified runTest.py based on input parameter

5. Multiple parameters are read from the Metrics.xml file and logged in the results.csv file along with the input parameters such as CHANNELBANDWIDTH\_MHz, TX\_ANTENNA\_COUNT, RX\_ANTENNA\_COUNT, INTER\_ARRIVAL\_TIME (micro sec).




Table 4: User need to modify these two parameters in Script files

6. Two script text files namely Script1.txt and Script2.txt are created with information to read each of the parameters from the Metrics.xml file. The variable OUTPUT\_PARAM\_COUNT is set to 2 as per the number of Script files.

# Script1.txt



Figure 26: The application throughput is to be logged for each simulation modified in Script1.txt

### Scritp2.txt




Figure 27: The Data Packets transmitted is to be logged for each simulation modified in Script2.txt

7. In the python script runTest.py, MetricsReader is called to log each parameter specified in the script text files separating the entries with a comma (","). If simulation crashes, without generating the output Metrics.xml, then "crash" message is written to the log for each output parameter. The input parameters that were varied during each simulation run are also logged in the results.csv file.

```
Solution

| Color | Co
```

Figure 28: Modify python script runTest.py file

8. The simulation Configuration file and all the output files associated with each simulation run is saved to folders with name including the bandwidth and DL MIMO count values that were used during each simulation run.




Figure 29: Modify python script runTest.py file

9. Multi-Parameter Sweeping process is started by opening command prompt in the directory of the Multi-Parameter-Sweeping project and starting the python script as shown below:

### **Python Script:**



Figure 30: Running Python Script using cmd Prompt

This starts the Multi-Parameter-Sweeping process which runs NetSim simulations iteratively for different combinations of input parameters.

At the end of the process the Multi-Parameter-Sweeping folder will have the following file and folders created:




Figure 31: After Simulation Multi-Parameter-Sweeping folder contains output files like result.scv, Data etc

10. **Data**: The Data directory contains multiple output folders with the output files associated with each simulation run.




Figure 32: Based on input parameter Configuration.netsim and other files created in output folder

- **IOPath**: Used for storing the Configuration.netsim file and the simulation files generated during each simulation run.
- **Result.csv**: This is the output log which contains the parameter varied during each simulation run and the output parameter associated with each run.




Figure 33: Based on script result stored in result.csv file